

This page is also available in **2 other languages**

Change language

English

◇

LANGUAGE

FUNCTIONS

VARIABLES

STRUCTURE

LIBRARIES

IOT CLOUD API

GLOSSARY

The Arduino Reference text is licensed under a [Creative Commons Attribution-Share Alike 3.0 License](#).

Find anything that can be improved? [Suggest corrections and new documentation via GitHub](#).

Doubts on how to use Github? Learn everything you need to know in [this tutorial](#).

Last Revision: 2023/11/20

Last Build: 2024/05/01

EDIT THIS PAGE

Reference > Language > Functions > External interrupts > Attachinterrupt

# attachInterrupt()

[External Interrupts]

## Description

### Digital Pins With Interrupts

The first parameter to `attachInterrupt()` is an interrupt number. Normally you should use `digitalPinToInterrupt(pin)` to translate the actual digital pin to the specific interrupt number. For example, if you connect to pin 3, use `digitalPinToInterrupt(3)` as the first parameter to `attachInterrupt()`.

BOARD	DIGITAL PINS USABLE FOR INTERRUPTS	NOTES
Uno Rev3, Nano, Mini, other 328-based	2, 3	
UNO R4 Minima, UNO R4 WiFi	2, 3	
Uno WiFi Rev2, Nano Every	All digital pins	
Mega, Mega2560, MegaADK	2, 3, 18, 19, 20, 21	(pins 20 & 21 are not available to use for interrupts while they are used for I2C communication; the pins also have external pull-ups that cannot be disabled)

Help

Micro, Leonardo	0, 1, 2, 3, 7	
Zero	0-3, 5-13, A0-A5	Pin 4 cannot be used as an interrupt.
MKR Family boards	0, 1, 4, 5, 6, 7, 8, 9, A1, A2	
Nano 33 IoT	2, 3, 9, 10, 11, 13, A1, A5, A7	
Nano 33 BLE, Nano 33 BLE Sense (rev 1 & 2)	all pins	
Nano RP2040 Connect	0-13, A0-A5	
Nano ESP32	all pins	
GIGA R1 WiFi	all pins	
Due	all digital pins	
101	all digital pins	(Only pins 2, 5, 7, 8, 10, 11, 12, 13 work with <b>CHANGE</b> ))

## Notes and Warnings

### Note

Inside the attached function, `delay()` won't work and the value returned `millis()` will not increment. Serial data received while in the function may be lost. You should declare as `volatile` any variables that you modify within the attached function. See the section on ISRs below for more information.

## Using Interrupts

Interrupts are useful for making things happen automatically in microcontroller programs and can help solve timing problems. Good tasks for using an interrupt may include reading a rotary encoder, or monitoring user input.

If you wanted to ensure that a program always caught a pulse from a rotary encoder, so that it never misses a pulse, it would be a very tricky

when they occurred. Other sensors have a similar interface dynamic too such as trying to read a sound sensor that is trying to catch a click, or an infrared slot sensor (photo-interrupter) trying to catch a coin drop. In all these situations, using an interrupt can free the microcontroller to get some other work done while not missing the input.

## About Interrupt Service Routines

ISRs are special kinds of functions that have some unique limitations that other functions do not have. An ISR cannot have any parameters, and they shouldn't return anything.

Generally, an ISR should be as short and fast as possible. If your sketch has multiple ISRs, only one can run at a time, other interrupts will be executed after the current one finishes in an order that depends on the priority they have. `millis()` relies on interrupts to count, so it will never increment inside an ISR. Since `delay()` requires interrupts to work, it will not work if called inside an ISR. `micros()` works initially but will start behaving erratically after 1-2 ms. `delayMicroseconds()` does not use any counter, so it will work as normal.

Typically global variables are used to pass data between an ISR and the main program. To make sure variables shared between an ISR and the main program are updated correctly, declare them as `volatile`.

For more information on interrupts, see [Nick Gammon's notes](#).

### Syntax

`attachInterrupt(digitalPinToInterrupt(pin), ISR, mode)` (recommended)  
`attachInterrupt(interrupt, ISR, mode)` (not recommended)  
`attachInterrupt(pin, ISR, mode)` (Not recommended. Additionally, this syntax only works on Arduino SAMD Boards, Uno WiFi Rev2, Due, and 101)

### Parameters

`interrupt`: the number of the interrupt. Allowed data types: `int`.

`pin`: the Arduino pin number.

`ISR`: the ISR to call when the interrupt occurs; this function must take no

`mode`: defines when the interrupt should be triggered. Four constants are predefined as valid values:

- **LOW** to trigger the interrupt whenever the pin is low,
- **CHANGE** to trigger the interrupt whenever the pin changes value
- **RISING** to trigger when the pin goes from low to high,
- **FALLING** for when the pin goes from high to low.

The Due, Zero and MKR1000 boards allow also:

- **HIGH** to trigger the interrupt whenever the pin is high.

## Returns

Nothing

## Example Code

```
const byte ledPin = 13;
const byte interruptPin = 2;
volatile byte state = LOW;

void setup() {
  pinMode(ledPin, OUTPUT);
  pinMode(interruptPin, INPUT_PULLUP);
  attachInterrupt(digitalPinToInterrupt(interruptPin), blink, CHANGE);
}

void loop() {
  digitalWrite(ledPin, state);
}

void blink() {
  state = !state;
}
```

## Interrupt Numbers

Normally you should use `digitalPinToInterrupt(pin)`, rather than place an interrupt number directly into your sketch. The specific pins with interrupt and their mapping to interrupt number varies for each type of board. Disuse of interrupt numbers may seem simple, but it can cause compatibility trouble when your sketch runs on a different board.

However, older sketches often have direct interrupt numbers. When number 0 (for digital pin 2) or number 1 (for digital pin 3) is used. The table below shows the available interrupt pins on various boards.

not always correspond directly to the interrupt numbering on the ATmega chip (e.g. int.0 corresponds to INT4 on the ATmega2560 chip).

BOARD	INT.0	INT.1	INT.2	INT.3	INT.4	INT.
Uno, Ethernet	2	3				
Mega2560	2	3	21	20	19	18
32u4 based (e.g Leonardo, Micro)	3	2	0	1	7	

For Uno WiFi Rev2, Due, Zero, MKR Family and 101 boards the **interrupt number = pin number**.

See also

Back to top

[Trademark](#)

[Help Center](#)

**NEWSLETTER**

[Contact Us](#)

[Whistleblowing](#)

[Distributors](#)

[Careers](#)

**FOLLOW US**

Enter your email to sign up

SUSCRIBIRSE

Help